



Synchronising files with your computer

SURFdrive manual

Author(s): SURFnet, edited for the EUR by J. Visser

Date: 02-10-2015



Contents

1	Synchronising files with your computer	3
1.1	Introduction	3
1.2	Downloading and installing the desktop client	3
1.3	Logging in to the desktop client	4
1.4	Extra features for the desktop client	6
1.5	Changing the settings	6



This publication is licensed under a [Creative Commons Attribution 3.0 Unported Licence](http://creativecommons.org/licenses/by/3.0/)
More information on the licence can be found on <http://creativecommons.org/licenses/by/3.0/>



1 Synchronising files with your computer

1.1 Introduction

With the desktop client, you can synchronise (sync) your files with a directory on your computer. Folders and files inside this directory will be kept in-sync with SURFdrive, which means that new and/or modified files will be downloaded and uploaded automatically. Also, if you delete a file from your SURFdrive it will be automatically removed from your hard drive. The desktop client is available for Windows, Mac OSX and Linux.

1.2 Downloading and installing the desktop client

You can install the desktop client **for your @wEURk** computer via the Application Catalog.

Open the Application Catalog from your desktop and search for SURFdrive. Then you will see the option to install the SURFdrive sync client (as is shown in the picture below).

The screenshot shows the 'Application Catalog' interface. At the top, there are tabs for 'Application Catalog', 'My Application Requests', and 'My Devices'. A search bar on the right contains the text 'surfdrive'. Below the search bar, a table displays search results for 'surfdrive' in All: 1. The table has columns for NAME, VERSION, PUBLISHER, CATEGORY, and REQUIRES APPROVAL. The first row shows 'SURFdrive' with version '1.8.4.24', publisher 'SURF', category 'Not suitable for RDS', and 'No' for approval. To the left of the table, there is a sidebar with 'BROWSE BY' options: 'Category' and 'Publisher'. Under 'Category', there is an 'All' option. Below the table, there is a section for 'SURF SURFdrive' with a description: 'SURFdrive is een persoonlijke cloudopslagdienst voor het Nederlandse hoger onderwijs en onderzoek; waarmee medewerkers en onderzoekers gemakkelijk bestanden kunnen opslaan, synchroniseren en delen. Log in met je ERNA account en krijg direct 100 GB tot je beschikking. Auto update disabled'. An 'INSTALL' button is visible in the bottom right corner of this section.

NAME	VERSION	PUBLISHER	CATEGORY	REQUIRES APPROVAL
SURFdrive	1.8.4.24	SURF	Not suitable for RDS	No

SURF SURFdrive
SURFdrive is een persoonlijke cloudopslagdienst voor het Nederlandse hoger onderwijs en onderzoek; waarmee medewerkers en onderzoekers gemakkelijk bestanden kunnen opslaan, synchroniseren en delen. Log in met je ERNA account en krijg direct 100 GB tot je beschikking. Auto update disabled

INSTALL

On the remote desktop only the SURFdrive web client is available.



For Windows, Mac OSX and Linux you can download the desktop client here: <http://surfdrive.surf.nl>. To install the desktop client:


For Windows: Run the installer.

For Mac OSX: Drag and drop the SURFdrive.app into your 'Applications' directory.

For Linux: Linux users can use the desktop client provided by ownCloud. Please refer to the installation instructions here: <http://owncloud.org/sync-clients/#linux>. **Note:** after installing the Linux client, you are asked to fill in a 'Server Address'. Please use: <https://surfdrive.surf.nl/files>.

Note: The desktop client will automatically create a folder on your hard drive where your files will be stored. This folder is called 'SURFdrive' and is located inside your home directory (On **Windows**: C:/Users/<username>/SURFdrive; On **Mac OSX**: /Users/<username>/SURFdrive).



To easily access this folder, you can create a shortcut on your desktop. Or, you can click the SURFdrive icon in the taskbar, and click 'Open folder SURFdrive'.



1.3 Logging in to the desktop client

After installing the desktop client, a login screen will appear (as is shown in the picture below). Select your institution from this screen and login through your institution. After logging in, the desktop client will start synchronising.

Synchronising files with your computer





1.4 Extra features for the desktop client

You can access extra features for the desktop client by clicking the icon in the status bar.



From here, you can:


- Open SURFdrive in your web browser
- Open the SURFdrive folder on your local hard drive
- See which files have recently been synced
- Access the settings for the desktop client
- Sign out of the desktop client
- Quit the desktop client

1.5 Changing the settings

Use the 'Settings' window to change some settings. The following settings can be changed:

Add Folder / Remove


By default, the desktop client synchronises the entire root folder of your SURFdrive and all of its subfolders and files. However, you can specify specific folders to sync instead of your entire root folder. To do this, first 'Remove' the default sync (**Note:** this will only remove the *sync*, not the files; all files that have been synced to your hard drive will be kept there). Then click 'Add Folder' and specify a folder on your local hard drive. After clicking 'Continue', you can select a specific folder from SURFdrive to sync with a local folder on your hard drive.



If you would like to sync your root folder and all its contents again, select SURFdrive (the topmost folder).

Edit Ignored Files

To prevent certain files and/or folders from syncing with your hard drive, you can use 'Edit Ignored Files'. Files or directories matching a pattern will not be synchronised. To add a new value, click 'Add' and enter a pattern. For example, if you would not like to synchronise files and folders with the word 'Shared' in it, you can specify that here.



Note: If you enable the checkbox in front of the pattern this file and/or folder will be removed from your SURFdrive.




There is a system wide list of default ignore patterns. These global defaults cannot be directly modified within the editor. Hovering with the mouse will reveal the location of the global exclude definition file.

Note: Modifying the global exclude definition file might render the client unusable or cause undesired behaviour.

Activity

Under the 'Activity' tab you can see a log of the syncing activity.



If for some reason files and/or folders are not synchronised you can refer to this log to find out if there are any errors.

Network

This tab consolidates 'Proxy Settings' and 'Bandwidth Limiting'.

You can change the following proxy settings:

No Proxy: Check this if the SURFdrive client should circumvent the default proxy configured on the system.

Use system proxy: This is the default setting; it will follow the system proxy settings. On Linux this will only pick up the value of the variable `http_proxy`.

Specify proxy manually as: Allows you to customize the proxy settings.

- **Host:** Enter the hostname or IP address of your proxy server, followed by the port number. HTTP proxies usually listen on Ports 8080 (default) or 3128. SOCKS server usually listen on port 1080.



- **Proxy Server requires authentication:** Should be checked if the proxy server does not allow anonymous usage. If checked, a username and password must be provided.

With bandwidth limiting you ensure the desktop client is not using more bandwidth than you specify. This might come in handy if you have a slow connection. You can limit your download and your upload bandwidth to a certain amount, specified in KB/s. You can also let the desktop client limit your upload bandwidth automatically: then, uploading will only take place as long as no other applications are uploading something.